

29.01. Synchronisation Sites

Synchronisation Sites, often simply called *Sync sites* or *Sites*, are configured for each device that is running mSupply that is using the synchronisation system. The synchronisation system ensures that all data on remote sites are synced to the central server.

Accessing Sync Sites

TODO: Describe site Output

Creating New Sync Sites

Editing Sync Sites

Permissions

TODO: Describe the user permissions required to access sync

Editing sync sites

TODO: Describe every field of Site Input

Site type

The site type simply indicates the intent to synchronise the sync site with mSupply Desktop or mSupply Mobile. When a remote site synchronises it will update the value of this. As of [v4.12](#), this setting has no functionality. Functionality around this is planned for the future.

Creating Sync Sites

Instructions and gotchas on creating sync sites ===== Deleting Sync Sites ===== Instructions and gotchas on creating sync sites

Remote Site Editing

All explanation of what the site editing is on the remote site -

Enabling Sync

Sync Mirror Setup

Sync Site Wizard

The sync site wizard is a tool to quickly create a sync site for a particular store. It does all the behind the scenes work for you, making sure that sync settings are updated for the store you are moving as well as for all the stores it has visible.



This Sync site wizard only allows a single store to be created on a sync site. However, after that is done, you can [Move a store from one sync site to another](#).

Before you use it


To use the sync site wizard you must:


- be on the central server machine
- have permission to “add/edit sync sites” (see the [25.15. Managing users](#) page for details on setting user permissions)

If you do not meet these criteria, you will be shown a warning and the wizard will not open.

Using the wizard

Choose *Special > Create sync site...* from the menus. This window will open:



 If the sync site is Mobile, then delete any Supplier Requisitions where Status = sg before the store is moved!

Selecting a store

First select a store. You can search in the **Store name** field by typing the first few characters of the store name and pressing the Tab key on the keyboard. This will present a list of stores starting with names starting with what you typed to choose from, or if there is only one match it will just be selected for you. No matches will prompt “try again”. You can use “@” as a wild card to get all stores available.

synchronisation.

The site name must also be unique. You may enter any text here. You may want to indicate what facility it is based in or what device it is.

Site password

The site password is used along with the site name when configuring a device to use the synchronisation system.

Make sure it is strong and record the password in a secure manner. We recommend a password manager like [Bitwarden](#).

If you would like Sussol to be able to provide support, the site name and password will need to be recorded in Sussol's secure credentials repository. Please consult with Sussol on how to communicate the credentials in a secure manner.



Please don't send the credentials together in an email, this is not secure. At least send them in separate emails but far better is to use an email to send one part and Skype, Telegram or WhatsApp or similar to send the other.

Previous: [29. Synchronisation](#) | | Next: [29.04. Sync Site Export](#)

From:

<https://docs.msupply.org.nz/docs/> - **mSupply documentation wiki**

Permanent link:

https://docs.msupply.org.nz/docs/synchronisation:site_wizard?rev=1644274049

Last update: **2022/02/07 22:47**

